

# Setting up POP and SMTP on IIS6.0 for use with GoldMine E-mail

Copyright © 2004 FrontRange Solutions Inc.

---

**Author:** Robert Comstock

**Department:** Technical Support

**Created:** March 4, 2004

**Last Updated:** April 2, 2004

## Copyright

*Copyright © 2004 FrontRange Solutions Inc. All Rights Reserved. GoldMine,, HEAT and other FrontRange products and brands are registered trademarks or trademarks of FrontRange Solutions Inc. in the U.S. and/or other countries. Other products and brands are registered trademarks or trademarks of their respective owners/companies.*

*USE OF THE SOFTWARE DESCRIBED IN THIS PAPER AND ITS RELATED USER DOCUMENTATION ARE SUBJECT TO THE TERMS AND CONDITIONS OF THE APPLICABLE END-USER LICENSE AGREEMENT (EULA).*

The information contained in this document is provided “as is” without warranty of any kind. To the maximum extent permitted by applicable law, FrontRange Solutions disclaims all warranties, either express or implied, including the warranties for merchantability and fitness for a particular purpose; and in no event shall FrontRange Solutions or its suppliers be liable for any damages whatsoever including direct, indirect, incidental, consequential, loss of business profits or special damages, even if advised of the possibility of such damages.

# Table of Contents

COPYRIGHT ..... 2

**SETTING UP POP AND SMTP ON IIS6.0 FOR USE WITH GOLDMINE E-MAIL..... 4**

    CONFIGURING THE MAIL SERVER ROLE ..... 4

    CONFIGURING THE SMTP SERVICE ..... 4

    CONFIGURING THE POP3 SERVICE ..... 4

    CONFIGURING GOLDMINE CLIENT ..... 5

# Setting up POP and SMTP on IIS6.0 for use with GoldMine E-mail

Note: This document does not cover installing IIS 6.0. Refer to Microsoft documentation for the correct setup procedures.

## Configuring the Mail Server Role

1. Open the *Configure Your Server Wizard*. (**Start>>Control Panel>>Administrative Tools>>Configure Your Server Wizard**)
2. On the *Welcome to the Configure Your Server Wizard* page, click **Next**.
3. On the *Preliminary Steps* page, click **Next**.
4. On the *Server Role* page, select **Mail Server (POP3, SMTP)**, click **Next**.
5. On the *Configure POP3 Service* page, select **Local Windows Account** for *Authentication method*, enter **<Computersname>.domain name** for *E-mail domain name*, and click **Next**.
6. On the *Summary of Selections* page, click **Next**. If prompted to insert the Windows Server 2003 CD, navigate to the CD drive where the Windows 2003 CD is located.
7. On the *This Server is now a Mail Server* page, click **Finish**.

## Configuring the SMTP Service

### Configuring Security

1. Open the *Internet Information Services (IIS) Manager*.
2. Expand *Internet Information Services (IIS)* and then **<Your Computer>**.
3. Right-click *Default SMTP Virtual Server*, and select **Properties**.
4. Click the **Access** tab, and under *Access control*, click **Authentication**.
5. Check *Integrated Windows Authentication*, and click **OK**.
6. Under *Relay restrictions*, click **Relay**.
7. Verify that *Allow all computers which successfully authenticate to relay, regardless of the list above* is checked, and click **OK** twice.

## Configuring the POP3 Service

### Verify POP3 Service Authentication

1. Click **Start>>Administrative Tools**, then the **POP3 Service**.
2. Right-click **<Computersname>**, and select **Properties**.
3. Verify that *Authentication Method* is **Local Windows Account**.

## Creating a Mailbox

1. Click **Start>>Administrative Tools**, then the **POP3 Service**.
2. Expand *<Computername>*, then *<Computername>.domain name*.
3. Right-click *<Computername>.domain name*, select **New>>Mailbox**.
4. Enter **<Your name>** for *Mailbox Name*, enter and confirm a password of **P@ssw0rd**, click **OK**.
5. If a POP3 Service message appears, check *Do not show this message again* and click **OK**.

## Configuring GoldMine Client

1. Open GoldMine.
2. Select **Edit>>Preferences**.
3. Click the **Internet tab>>Accounts>>New**.
4. Enter an account name.
5. Enter **<computername>** for the *POP3 server*.
6. Enter **<computername>.domain name** for the *SMTP server*.
7. Enter **<your name>** for the username. This was created in step 4 of creating a mailbox.
8. Enter the password created in step 4 of creating a mailbox for the password
9. Enter **<your name>@<computer name>.domain name** for the *return address*.
10. Select **SPA** for the *authentication*.
11. Click the **Advanced Options**
12. Select *The server requires authentication*
13. Select the *SPA* radio button
14. Click **OK** four times